


VITRO



GUIDE TO THE VITRO APP



FOR IPHONES

V1.0 (08/21)

CATALOG

01

**DOWNLOAD &
REGISTER**

02

PAIR DEVICE

03

**AGE
VERIFICATION**

04

**GETTING
STARTED**

PART ONE

**DOWNLOAD &
REGISTER**



Download on the
App Store

DOWNLOAD APP

Download the Bluefy app on the App Store.



SIGN UP

The image shows a smartphone screen with the Vitro app's sign-up page. The page has a light blue background and a white border. At the top, there's a back arrow and the title 'Sign up'. Below the title, there's an 'Email' field with a 'Send' button. Underneath is a 'Registration code from email' field with a placeholder 'Valid within three minutes'. Then, there are 'Password' and 'Confirm Password' fields, both with a '6+ characters' requirement and a strength indicator. At the bottom, there's a checkbox for 'By signing up, I agree to the [Term of Use](#) and [Privacy Policy](#)' and a 'Sign up' button. The phone's status bar at the top shows the time as 4:27 PM and 51% battery. The bottom of the phone shows the iOS home indicator and a dock with icons for back, home, search, and app drawer.

Open the Bluefy app. Input url *app.vitroworld.com* and enter.


Use your email to create an account.

You will receive a **registration code** to finish the set-up process.

Then sign in to your account.

PART TWO


PAIR DEVICE




PAIR DEVICE

Quickly press the power button 5 times to turn on the device. Ensure your phone has Bluetooth turned on.

Use your phone to pair to the device by selecting the unique device ID (find it on the bottom of your device).




PAIR DEVICE



Select your user ID.

PAIR DEVICE




Quickly click the power button 3 times on your device to finish the pairing.

PART THREE

AGE

VERIFICATION




AGE VERIFICATION

In accordance with federal law, the sale of tobacco products is prohibited to individuals under the age of 21.

Accordingly, users in the United States must download the VITRO app and complete the age verification process prior to using the device.

VITRO has partnered with <https://agechecker.net> to verify user age. Please follow the instruction as shown to complete age verification.

Please make sure all your information is correct before submit or you may fail to verify.



AGE VERIFICATION

Your age was successfully verified.

PART FOUR
**GETTING
STARTED**

INPUT E-LIQUID INFO

5:30 PM 44%

app.vitroworld.com

My E-Liquid

Brand

Nicotine

PG/VG

Please only use non-salt e-liquid products that have received a premarket tobacco product application (PMTA) marketing approval from the FDA.

Send

Enter your e-liquid details into the app to enable better feedback from the app.

HOME SCREEN

POWER CONTROL

Tap the power icon to switch the power level between low/medium/high.



MY E-LIQUID

We suggest keeping our e-liquid information updated especially when you change to a new e-liquid to ensure accurate vaping data.

**MY
E-Liquid**

VITRO

BATTERY

You can quickly check the battery information by tapping the battery icon.



E-LIQUID

Tap the e-liquid icon to check the using suggestion for you.





COIL PUFFS

Tap the coil icon to check your coil info and set your puffs plan.




PUFFS OF THE DAY

Actual
Plan



HOME SCREEN

VITRO



BATTERY (LOW) ALERT


The device will vibrate with notification on your VITRO app when the battery level is below 10%. You can tap to turn it on or off.

You can quickly check the battery information by tapping the battery icon.

HOME SCREEN

VITRO

Tap the e-liquid icon to check the using suggestion for you.




COIL PROTECTION ALERT

The device will vibrate when coil protection has been activated in the app. You will also receive a notification in the VITRO app. Please check the coil condition and remaining e-liquid in the cartridge. You can tap to turn it on or off.

HOME SCREEN

VITRO

You can tap to lock/unlock. When it is locked, you are unable to adjust your puffs plan.




COIL PUFFS ALERT

Scroll the bar to set your coil puffs pan. The device will vibrate when your actual puffs reach your set puff value in the app. Please check the coil condition or update the puff setting accordingly.

You can check your actual vaping info on the coil you're currently using.


You can quickly check the battery information by tapping the battery icon.

DATA - MY HISTORY




You can check your puff count and vaping time by day, week, or month.

DATA - MY PLAN





Tap the control knob in the app to set your vaping plan for the next 1, 7 or 30 days. The control knob can be rotated clockwise to increase and counterclockwise to decrease the vaping plan.


MY DEVICE




Here you can check the main information about your device, including the cartridge, the coil, the battery etc. You can switch to bind with another VITRO device or choose to unbind the current device with this account. Also if you cannot find your device, you can try 'Find My Device'.



Cartridge Information




Battery Information




Coil Information

MY DEVICE - UNBIND DEVICE



If you choose to unbind your device, your vaping data will be deleted. The device will be reset to default. You need to go through 'age verification' again when you bind it to a new account.

PROFILE



Here you can set your profile photo, contact us and check the messages. Also you can check the App version and Firmware version. You can turn on/off the alerts, which is the same as you can find on the home screen.

Lock Device: When it is enabled, you cannot use the device. This function is designed for safety concerns in case you need.


PROFILE - CONTACT US

The image shows a white smartphone with a grey home button. The screen displays a web browser interface for 'app.vitroworld.com'. The status bar at the top shows the time as 4:40 PM and battery at 47%. The page title is 'Contact Us'. The main content area has a light blue background and contains the following text: 'We'd love to hear from you and would be happy to answer any questions you have or otherwise provide additional information.' Below this is a 'Message to' section with the email address 'service@vitroworld.com'. A prompt asks the user to 'Please complete the following info so that we can help you.' followed by a large text input field with the placeholder 'Please enter your questions here'. Below the text field is a 'Your Phone Number' section with a text input field containing the placeholder 'Optional'. At the bottom of the form is a blue 'Send' button. The browser's bottom navigation bar shows icons for back, home, search, and tabs.

If you have any questions, you can contact us at any time. Our service team will get to you asap.

Please check the reply in the inbox of your email.

VITRO



THANK YOU